

Make your own stable fly trap

The pest

Stable flies are a problem in Perth, Western Australia, because the Swan Coastal Plain provides perfect conditions (sandy soils, temperate climate, rotting organic material and nearby hosts) for stable fly to breed in high numbers.



Waste management is the most successful method to control stable fly numbers; however sticky traps can help to reduce the numbers of adult flies that may be causing annoyance around your property.

You can make a simple sticky 'Williams' trap with a white board and a non-drying glue and placing it near livestock and horses. Boards with a white sticky surface will attract them, as they like to rest on a cool, vertical surface after a blood meal.

The boards can be reused by removing the old coating (and dead flies) and reapplying a fresh coat of non-drying glue. Multiple boards, cleared daily and re-painted, can remove several thousand stable flies.



Traps can reduce stable fly numbers

What you need to do

Step 1: Materials required

Visit your local hardware store.

Board

There are many different types of boards you can purchase.

You can use corflute, melamine, aligloss, acrylic sheets, high density polyethylene boards, masonite or stainless steel minisheets, which come in sizes from 600 mm x 600 mm up to 900 mm x 600 mm and 1200 mm x 900 mm.

Glue

One litre will of glue will cover up to 15 traps.



Sticky traps are specific to stable flies and catch little else

• Make your own non-drying glue – an internet search will provide recipes for making homemade non-drying glue.

- Suitable commercial non-drying glue includes:
 - Catchmaster Tree Banding Insect Barrier or Olson Sticky Stuff Brush on Insect Trap Coating non-drying glue, such as Stikem®,
 - o Amazon Australia advertises Tangle Foot Sticky Glue Coating.
 - Catchmaster Tree Banding Insect Barrier DIY Kit, which is a 430 g bucket with a spreader
- An alternative is to purchase 100 m rolls of white or clear film that have non-drying glue on both sides. You simply stick the film onto any whiteboards and peel off when covered with flies. The rolls of film can be purchased in either 15 cm or 30 cm wide strips, so you can put several strips on the white board depending upon the size of the board you choose.
- Star picket to mount board

Step 3: Apply the glue

- Heat the non-drying glue on a hot plate or over hot water so it thins out and can be easily spread.
- Cover both sides of the board with the glue.

Step 4: Place in paddock

- Secure the board to a star picket, so that it is about 1 m from the ground to avoid it being covered in dirt and dust.
- Place near livestock and horses
- Monitor and when the white board is covered with flies, remove the glue with a paint scraper before re-applying.



Sticky trap set up and ready for use

For more information and strategies on managing stable fly see dpird.wa.gov.au/stablefly.

If you are experiencing problems with stable fly, please report to your local government authority.

Important Disclaimer

The Chief Executive Officer of the Department of Primary Industries and Regional Development and the State of Western Australia accept no liability whatsoever by reason of negligence or otherwise arising from the use or release of this information or any part of it.

Copyright © State of Western Australia (Department of Primary Industries and Regional Development) 2025